
THE BACKUP MASTER
(C) COPYRIGHT 1986 * REEVE SOFTWARE

REEVE SOFTWARE
29W150 OLD FARM LANE
WARRENVILLE, IL 60555
(312) 393-2317

* STEP-BY-STEP INSTRUCTIONS *

FOLLOW THESE INSTRUCTIONS STEP
BY STEP WHEN USING THE BACKUP
MASTER:

PURPOSE-

THE BACKUP MASTER WAS DESIGNED TO
ALLOW USERS TO BACKUP THEIR SOFTWARE
WITHOUT HAVING TO WAIT FOR THE
MANUFACTURER OF THE PROGRAM TO
REPLACE IT OR PAY AN UNREASONABLE
FEE FOR A BACKUP.

UPDATES-

WE WILL TRY TO PROVIDE UPDATES TO
THIS PROGRAM AS NECESSARY AT A
REASONABLE COST.

* LOADING INSTRUCTIONS *

- 1) TURN OFF YOUR COMPUTER, TURN ON
YOUR DISK DRIVE, AND TELEVISION
OR MONITOR.
- 2) INSERT THE BACKUP MASTER INTO
DRIVE NUMBER 1, AND TURN ON
YOUR COMPUTER (HOLD DOWN OPTION
UNTIL THE SCREEN TURNS BLUE
IF BASIC IS NOT DESIRED).
- 3) THE PROGRAM SHOULD LOAD AND
GREET YOU WITH ITS TITLE SCREEN!
- 4) IF THE PROGRAM DISK REFUSES TO
LOAD, OR YOU HAVE PROBLEMS
USING IT PLEASE TRY IT OUT
ON ANOTHER COMPUTER BEFORE
CONTACTING US.

BE SURE TO READ THROUGH THESE
INSTRUCTIONS AT LEAST ONCE BEFORE
USING THE BACKUP MASTER!

- 1) SECTOR COPY EACH DISK THAT IS
PART OF THE PROGRAM THAT YOU WISH
TO BACK UP. TO SECTOR COPY
A DISK, FORMAT A BLANK DISK IN
SINGLE DENSITY USING ATARI DOS
AND THEN USE THE SECTOR COPIER
(OPTION 5) PROVIDED AS PART OF
THE BACKUP MASTER.

- 2) FORMAT ANOTHER DISK USING ATARI
DOS AS IN STEP 1. LOAD THE
BACKUP MASTER, INSERT YOUR
NEWLY FORMATTED DISK INTO DRIVE
1, AND SELECT OPTION 1 TO
INITIALIZE THE DISK. THIS DISK
WILL BE REFERRED TO AS YOUR
BOOT LOAD DISK.

- 3) DECIDE WHETHER THE PROGRAM YOU
WANT TO BACKUP REQUIRES BASIC OR
NOT, AND RELOAD THE BACKUP MASTER
WITH OR WITHOUT BASIC.

- 4)
 - A) PLACE SIDE 1 OF THE PROGRAM THAT
YOU WISH TO BACK UP INTO DRIVE
1, AND SELECT OPTION 2 (CREATE
SECTOR MAP).
 - B) YOUR COMPUTER SHOULD LOAD THE
PROGRAM THAT YOU ARE COPYING.
 - C) ONCE THE PROGRAM LOADS, YOUR
DRIVE SHOULD STOP.
 - D) AT THIS TIME INSERT THE BACK SIDE
OF THE BACKUP MASTER INTO DRIVE
ONE AND PRESS SYSTEM RESET TO
LOAD THE PROGRAM THAT SAVES YOUR
SECTOR/STATUS MAP ONTO YOUR
BOOT LOAD DISK.

NOTE: THE BEST WAY TO GET A GOOD
SECTOR MAP IS BY WAITING FOR
THE PROGRAM TO QUIT LOADING!
THE DRIVE MUST STOP BEFORE
INSERTING OUR MAP DUMP PROGRAM
INTO DRIVE NUMBER 1.

5) CREATE A STATUS MAP IN THE SAME WAY THAT YOU CREATED THE SECTOR MAP IN STEP 4 BY USING OPTION 3.

6) NOW RELOAD THE BACKUP MASTER, AND USE OPTION 4 TO COPY DATA FROM SIDE 1 OF THE PROGRAM THAT YOU WISH TO COPY TO YOUR BOOT LOAD DISK. *w/o BASIC*

7) TO USE YOUR BACK UP COPY:

- A) INSERT YOUR BOOT LOAD DISK INTO DRIVE 1.
- B) SELECT BASIC IF NEEDED, AND LOAD THE PROGRAM IN THE SAME WAY THAT YOU LOAD THE ORIGINAL.
- C) WHEN YOU GET TO THE POINT THAT YOU STOPPED TO CREATE YOUR SECTOR MAP CHANGE DISKS BY INSERTING YOUR SECTOR COPY OF SIDE 1 OF THE PROGRAM INTO DRIVE 1.

* OTHER CHOICES *

1) PRESS P TO DIS-ENGAGE PRO*MODE! YOU WILL THEN SEE A MINUS SIGN APPEAR. THIS MAY BE NECESSARY FOR A FEW PROGRAMS.

2) USING TWO DRIVES:
YOU CAN USE TWO DISK DRIVES BY PRESSING D (FOR DRIVES). THIS CHOICE IS USED BY OPTIONS 4 AND 5.

A) WHEN USING TWO DRIVES WITH OPTION 4 YOU WILL FIRST BE ASKED TO PLACE YOUR BOOT LOAD DISK INTO DRIVE 1. AFTER YOUR PRESS START AND THE SECTOR MAP HAS LOADED INTO MEMORY YOU SHOULD THEN MOVE YOUR BOOT LOAD DISK TO DRIVE 2, AND PLACE SIDE 1 OF THE PROGRAM YOU WISH TO COPY INTO DRIVE 1.

B) WHEN USING TWO DRIVES WITH OPTION 5 PLACE YOUR SOURCE DISK IN DRIVE 1, AND YOUR DESTINATION (BLANK FORMATTED) DISK INTO DRIVE TWO.

IF YOU FOLLOW THESE STEPS YOU SHOULD BE ABLE TO COPY MOST DISKS. IF YOU COME ACROSS A PROGRAM THAT CAN NOT BE COPIED USING THESE METHODS LET US KNOW.

PLEASE DO NOT ABUSE THE POWER OF THIS PROGRAM!

WARRANTY-

IF THE BACKUP MASTER IS FOUND TO BE DEFECTIVE WITHIN THIRTY DAYS OF PURCHASE PLEASE RETURN IT TO US WITH YOUR COMPLETED WARRANTY CARD, AND A COPY OF YOUR RECEIPT. WE WILL IMMEDIATELY SEND OUT A REPLACEMENT. IF THE BACKUP MASTER FAILS TO WORK AFTER THIRTY DAYS THERE IS A \$2 SERVICE CHARGE. THIS WARRANTY ONLY APPLIES SO LONG AS THE DISK HAS BEEN TREATED PROPERLY.